

AlsaPlayer

0.99.80

Generated by Doxygen 1.5.9

Tue Aug 25 10:02:05 2009

Contents

1	Data Structure Index	1
1.1	Data Structures	1
2	File Index	3
2.1	File List	3
3	Data Structure Documentation	5
3.1	_input_object Struct Reference	5
3.1.1	Detailed Description	5
3.1.2	Field Documentation	6
3.1.2.1	flags	6
3.1.2.2	frame_size	6
3.1.2.3	local_data	6
3.1.2.4	nr_channels	6
3.1.2.5	nr_frames	6
3.1.2.6	nr_tracks	6
3.1.2.7	object_mutex	6
3.1.2.8	path	6
3.1.2.9	ready	6
3.2	_input_plugin Struct Reference	8
3.2.1	Field Documentation	8
3.2.1.1	author	8
3.2.1.2	can_handle	8

3.2.1.3	channels	8
3.2.1.4	close	8
3.2.1.5	flags	8
3.2.1.6	frame_seek	9
3.2.1.7	frame_size	9
3.2.1.8	frame_to_sec	9
3.2.1.9	handle	9
3.2.1.10	init	9
3.2.1.11	name	9
3.2.1.12	nr_frames	9
3.2.1.13	nr_tracks	9
3.2.1.14	open	9
3.2.1.15	play_frame	9
3.2.1.16	plugin_handle	9
3.2.1.17	sample_rate	9
3.2.1.18	shutdown	9
3.2.1.19	stream_info	9
3.2.1.20	track_seek	9
3.2.1.21	version	9
3.3	_interface_plugin Struct Reference	10
3.3.1	Field Documentation	10
3.3.1.1	author	10
3.3.1.2	close	10
3.3.1.3	handle	10
3.3.1.4	init	10
3.3.1.5	name	10
3.3.1.6	running	10
3.3.1.7	start	10
3.3.1.8	stop	10
3.3.1.9	version	10
3.4	_output_plugin Struct Reference	11

3.4.1	Field Documentation	11
3.4.1.1	author	11
3.4.1.2	close	11
3.4.1.3	get_latency	11
3.4.1.4	get_queue_count	11
3.4.1.5	init	11
3.4.1.6	name	12
3.4.1.7	open	12
3.4.1.8	set_buffer	12
3.4.1.9	set_sample_rate	12
3.4.1.10	start_callbacks	12
3.4.1.11	version	12
3.4.1.12	write	13
3.5	_scope_plugin Struct Reference	14
3.5.1	Detailed Description	14
3.5.2	Field Documentation	14
3.5.2.1	author	14
3.5.2.2	handle	14
3.5.2.3	init	14
3.5.2.4	name	14
3.5.2.5	running	15
3.5.2.6	set_data	15
3.5.2.7	set_fft	15
3.5.2.8	shutdown	15
3.5.2.9	start	15
3.5.2.10	stop	15
3.5.2.11	version	15
4	File Documentation	17
4.1	input_plugin.h File Reference	17
4.1.1	Define Documentation	18

4.1.1.1	INPUT_PLUGIN_BASE_VERSION	18
4.1.1.2	INPUT_PLUGIN_VERSION	18
4.1.1.3	P_BUFFERING	18
4.1.1.4	P_FILEBASED	18
4.1.1.5	P_PERFECTSEEK	19
4.1.1.6	P_REENTRANT	19
4.1.1.7	P_SEEK	19
4.1.1.8	P_STREAMBASED	19
4.1.2	Typedef Documentation	19
4.1.2.1	input_can_handle_type	19
4.1.2.2	input_channels_type	19
4.1.2.3	input_close_type	19
4.1.2.4	input_flags_type	20
4.1.2.5	input_frame_seek_type	20
4.1.2.6	input_frame_size_type	20
4.1.2.7	input_frame_to_sec_type	20
4.1.2.8	input_init_type	20
4.1.2.9	input_nr_frames_type	20
4.1.2.10	input_nr_tracks_type	21
4.1.2.11	input_object	21
4.1.2.12	input_open_type	21
4.1.2.13	input_play_frame_type	21
4.1.2.14	input_plugin	21
4.1.2.15	input_plugin_handle_type	21
4.1.2.16	input_plugin_info_type	21
4.1.2.17	input_sample_rate_type	22
4.1.2.18	input_shutdown_type	22
4.1.2.19	input_stream_info_type	22
4.1.2.20	input_track_seek_type	22
4.1.2.21	input_version_type	22
4.2	interface_plugin.h File Reference	23

4.2.1	Define Documentation	24
4.2.1.1	INTERFACE_PLUGIN_BASE_VERSION	24
4.2.1.2	INTERFACE_PLUGIN_VERSION	24
4.2.2	Typedef Documentation	24
4.2.2.1	interface_close_type	24
4.2.2.2	interface_init_type	24
4.2.2.3	interface_plugin	24
4.2.2.4	interface_plugin_info_type	24
4.2.2.5	interface_running_type	24
4.2.2.6	interface_start_type	24
4.2.2.7	interface_stop_type	24
4.2.2.8	interface_version_type	24
4.3	output_plugin.h File Reference	25
4.3.1	Define Documentation	26
4.3.1.1	OUTPUT_PLUGIN_BASE_VERSION	26
4.3.1.2	OUTPUT_PLUGIN_VERSION	26
4.3.2	Typedef Documentation	26
4.3.2.1	output_close_type	26
4.3.2.2	output_get_latency_type	26
4.3.2.3	output_get_queue_count_type	26
4.3.2.4	output_init_type	26
4.3.2.5	output_open_type	26
4.3.2.6	output_plugin	26
4.3.2.7	output_plugin_info_type	26
4.3.2.8	output_set_buffer_type	26
4.3.2.9	output_set_sample_rate_type	26
4.3.2.10	output_start_callbacks_type	26
4.3.2.11	output_version_type	26
4.3.2.12	output_write_type	26
4.4	scope_plugin.h File Reference	27
4.4.1	Define Documentation	27

4.4.1.1	SCOPE_BG_BLUE	27
4.4.1.2	SCOPE_BG_GREEN	27
4.4.1.3	SCOPE_BG_RED	28
4.4.1.4	SCOPE_NICE	28
4.4.1.5	SCOPE_PLUGIN_BASE_VERSION	28
4.4.1.6	SCOPE_PLUGIN_VERSION	28
4.4.1.7	SCOPE_SLEEP	28
4.4.2	Typedef Documentation	28
4.4.2.1	scope_init_type	28
4.4.2.2	scope_plugin	29
4.4.2.3	scope_plugin_info_type	29
4.4.2.4	scope_running_type	29
4.4.2.5	scope_set_data_type	29
4.4.2.6	scope_set_fft_type	29
4.4.2.7	scope_shutdown_type	30
4.4.2.8	scope_start_type	30
4.4.2.9	scope_stop_type	30
4.4.2.10	scope_version_type	30

Chapter 1

Data Structure Index

1.1 Data Structures

Here are the data structures with brief descriptions:

_input_object	5
_input_plugin	8
_interface_plugin	10
_output_plugin	11
_scope_plugin	14

Chapter 2

File Index

2.1 File List

Here is a list of all files with brief descriptions:

input_plugin.h	17
interface_plugin.h	23
output_plugin.h	25
scope_plugin.h	27

Chapter 3

Data Structure Documentation

3.1 `_input_object` Struct Reference

```
#include <input_plugin.h>
```

Data Fields

- int `ready`
- int `flags`
- int `nr_frames`
- int `nr_tracks`
- int `nr_channels`
- int `frame_size`
- void * `local_data`
- char * `path`
- pthread_mutex_t `object_mutex`

3.1.1 Detailed Description

This is a structure that keeps frequently used parameters of an input instance. It also contains a pointer to any `local_data` that might be allocated by the plugin itself.

3.1.2 Field Documentation

3.1.2.1 `int _input_object::flags`

Stream specific flags that should be set in the `open()` call. Read the description of the `P_*` definitions for details.

3.1.2.2 `int _input_object::frame_size`

The frame size in bytes. `play_frame()` will be called with this value.

3.1.2.3 `void* _input_object::local_data`

If your plugin needs extra space for its own variables assign the allocated data structure to this pointer

3.1.2.4 `int _input_object::nr_channels`

The number of PCM channels in the stream. Should always be 2 at this time.

3.1.2.5 `int _input_object::nr_frames`

The total number of frames in the stream. Should be set in the `open()` call.

3.1.2.6 `int _input_object::nr_tracks`

The number of tracks, if any, in the stream. Should be set in the `open()` call.

3.1.2.7 `pthread_mutex_t _input_object::object_mutex`

The object mutex. Used to lock and unlock the data structures. Initialized and called from the HOST.

3.1.2.8 `char* _input_object::path`

Path of the currently played file

3.1.2.9 `int _input_object::ready`

Flag that should be set to 1 if your plugin is ready to accept `play_frame()` callback

The documentation for this struct was generated from the following file:

- [input_plugin.h](#)

3.2 `_input_plugin` Struct Reference

```
#include <input_plugin.h>
```

Data Fields

- `input_version_type` version
- `input_flags_type` flags
- `char *` name
- `char *` author
- `void *` handle
- `input_init_type` init
- `input_shutdown_type` shutdown
- `input_plugin_handle_type` plugin_handle
- `input_can_handle_type` can_handle
- `input_open_type` open
- `input_close_type` close
- `input_play_frame_type` play_frame
- `input_frame_seek_type` frame_seek
- `input_frame_size_type` frame_size
- `input_nr_frames_type` nr_frames
- `input_frame_to_sec_type` frame_to_sec
- `input_sample_rate_type` sample_rate
- `input_channels_type` channels
- `input_stream_info_type` stream_info
- `input_nr_tracks_type` nr_tracks
- `input_track_seek_type` track_seek

3.2.1 Field Documentation

3.2.1.1 `char* _input_plugin::author`

Should point to a character array containing the name of the author(s) of this plugin.

3.2.1.2 `input_can_handle_type _input_plugin::can_handle`

3.2.1.3 `input_channels_type _input_plugin::channels`

3.2.1.4 `input_close_type _input_plugin::close`

3.2.1.5 `input_flags_type _input_plugin::flags`

Fixed flags for the plugin (P_*)

3.2.1.6 `input_frame_seek_type _input_plugin::frame_seek`

3.2.1.7 `input_frame_size_type _input_plugin::frame_size`

3.2.1.8 `input_frame_to_sec_type _input_plugin::frame_to_sec`

3.2.1.9 `void* _input_plugin::handle`

`dlopen()` handle of this plugin. Filled in by the HOST.

3.2.1.10 `input_init_type _input_plugin::init`

3.2.1.11 `char* _input_plugin::name`

Should point to a character array containing the name of this plugin

3.2.1.12 `input_nr_frames_type _input_plugin::nr_frames`

3.2.1.13 `input_nr_tracks_type _input_plugin::nr_tracks`

3.2.1.14 `input_open_type _input_plugin::open`

3.2.1.15 `input_play_frame_type _input_plugin::play_frame`

3.2.1.16 `input_plugin_handle_type _input_plugin::plugin_handle`

3.2.1.17 `input_sample_rate_type _input_plugin::sample_rate`

3.2.1.18 `input_shutdown_type _input_plugin::shutdown`

3.2.1.19 `input_stream_info_type _input_plugin::stream_info`

3.2.1.20 `input_track_seek_type _input_plugin::track_seek`

3.2.1.21 `input_version_type _input_plugin::version`

Must be set to `INPUT_PLUGIN_VERSION`

The documentation for this struct was generated from the following file:

- [input_plugin.h](#)

3.3 `_interface_plugin` Struct Reference

```
#include <interface_plugin.h>
```

Data Fields

- [interface_version_type](#) version
- `char *` [name](#)
- `char *` [author](#)
- `void *` [handle](#)
- [interface_init_type](#) init
- [interface_start_type](#) start
- [interface_running_type](#) running
- [interface_stop_type](#) stop
- [interface_close_type](#) close

3.3.1 Field Documentation

3.3.1.1 `char* _interface_plugin::author`

3.3.1.2 `interface_close_type _interface_plugin::close`

3.3.1.3 `void* _interface_plugin::handle`

3.3.1.4 `interface_init_type _interface_plugin::init`

3.3.1.5 `char* _interface_plugin::name`

3.3.1.6 `interface_running_type _interface_plugin::running`

3.3.1.7 `interface_start_type _interface_plugin::start`

3.3.1.8 `interface_stop_type _interface_plugin::stop`

3.3.1.9 `interface_version_type _interface_plugin::version`

The documentation for this struct was generated from the following file:

- [interface_plugin.h](#)

3.4 _output_plugin Struct Reference

```
#include <output_plugin.h>
```

Data Fields

- [output_version_type](#) version
- char * [name](#)
- char * [author](#)
- [output_init_type](#) init
- [output_open_type](#) open
- [output_close_type](#) close
- [output_write_type](#) write
- [output_start_callbacks_type](#) start_callbacks
- [output_set_buffer_type](#) set_buffer
- [output_set_sample_rate_type](#) set_sample_rate
- [output_get_queue_count_type](#) get_queue_count
- [output_get_latency_type](#) get_latency

3.4.1 Field Documentation

3.4.1.1 char* _output_plugin::author

Author of the plugin

3.4.1.2 output_close_type _output_plugin::close

Close the output plugin

3.4.1.3 output_get_latency_type _output_plugin::get_latency

Returns the latency of the output device in bytes. This function is optional.

3.4.1.4 output_get_queue_count_type _output_plugin::get_queue_count

Returns the number of bytes pending in the hardware buffer of output device. This function is optional.

3.4.1.5 output_init_type _output_plugin::init

Initialize output plugin. Called before the plugin is opened for use

3.4.1.6 `char* _output_plugin::name`

Name of output plugin

3.4.1.7 `output_open_type _output_plugin::open`

Parameters:

path The path or device designation that should be used

Opens the output plugin. A value of 1 should be returned on success, 0 on failure.

3.4.1.8 `output_set_buffer_type _output_plugin::set_buffer`

Parameters:

frag_size Fragment size to use (in bytes)

frag_count Fragment count to use (in bytes)

channels Number of channels to use

Set up the output device with the given parameters. Some output devices do not accept such configurations in which case they should just be ignored, but still expect *frag_size* data chunks in the write function. A value of 1 should be returned on success, 0 on failure.

3.4.1.9 `output_set_sample_rate_type _output_plugin::set_sample_rate`

Parameters:

rate Sample rate to use

Set the sample rate of the output device. A value of 1 should be returned on success, 0 on failure.

3.4.1.10 `output_start_callbacks_type _output_plugin::start_callbacks`

Parameters:

data pointer to bufs structure in `AlsaNode`

This function is used for callback based plugins like JACK

3.4.1.11 `output_version_type _output_plugin::version`

Version of output plugin. Must be `OUTPUT_PLUGIN_VERSION`

3.4.1.12 output_write_type _output_plugin::write

Parameters:

data Buffer that contains the data Number of bytes that should be read from the buffer

Write out data to the output device. This is a byte count and will typically be the same size as a fragment. A value of 1 should be returned on success, 0 on failure.

The documentation for this struct was generated from the following file:

- [output_plugin.h](#)

3.5 `_scope_plugin` Struct Reference

```
#include <scope_plugin.h>
```

Data Fields

- `scope_version_type` `version`
- `char *` `name`
- `char *` `author`
- `void *` `handle`
- `scope_init_type` `init`
- `scope_start_type` `start`
- `scope_running_type` `running`
- `scope_stop_type` `stop`
- `scope_shutdown_type` `shutdown`
- `scope_set_data_type` `set_data`
- `scope_set_fft_type` `set_fft`

3.5.1 Detailed Description

You should declare a `scope_plugin` variable and populate it with pointers of the specific functions implemented by your scope

3.5.2 Field Documentation

3.5.2.1 `char* _scope_plugin::author`

Point to a character array with the name of the author(s) of the scope

3.5.2.2 `void* _scope_plugin::handle`

Pointer to a `dlopen()` handle. This is filled in by the HOST. Set to `NULL`.

3.5.2.3 `scope_init_type _scope_plugin::init`

Should point to the implementation of your `init()` function. Required by the HOST.

3.5.2.4 `char* _scope_plugin::name`

Point to a character array with the name of the scope

3.5.2.5 `scope_running_type _scope_plugin::running`

Should point to the implementation of your [running\(\)](#) function. Required by the HOST.

3.5.2.6 `scope_set_data_type _scope_plugin::set_data`

Should point to the function that collects PCM data. If you don't want PCM data set to NULL.

3.5.2.7 `scope_set_fft_type _scope_plugin::set_fft`

Should point to the function that collects FFT data. If you don't want FFT data set to NULL. NB. `set_data` and `set_fft` can't both be NULL, at least one must be set.

3.5.2.8 `scope_shutdown_type _scope_plugin::shutdown`

Should point to the implementation of your [shutdown\(\)](#) function. Required by the HOST.

3.5.2.9 `scope_start_type _scope_plugin::start`

Should point to the implementation of your [start\(\)](#) function. Required by the HOST.

3.5.2.10 `scope_stop_type _scope_plugin::stop`

Should point to the implementation of your [stop\(\)](#) function. Required by the HOST.

3.5.2.11 `scope_version_type _scope_plugin::version`

Set to `SCOPE_PLUGIN_VERSION`

The documentation for this struct was generated from the following file:

- [scope_plugin.h](#)

Chapter 4

File Documentation

4.1 input_plugin.h File Reference

```
#include "stream_info.h"
#include <pthread.h>
```

Data Structures

- struct [_input_object](#)
- struct [_input_plugin](#)

Defines

- #define [P_SEEK](#) 1
- #define [P_PERFECTSEEK](#) 2
- #define [P_REENTRANT](#) 4
- #define [P_FILEBASED](#) 8
- #define [P_STREAMBASED](#) 16
- #define [P_BUFFERING](#) 32
- #define [INPUT_PLUGIN_BASE_VERSION](#) 0x1000
- #define [INPUT_PLUGIN_VERSION](#) (INPUT_PLUGIN_BASE_VERSION + 16)

Typedefs

- typedef struct [_input_object](#) [input_object](#)

- typedef int [input_version_type](#)
- typedef int [input_flags_type](#)
- typedef int(* [input_init_type](#))(void)
- typedef void(* [input_shutdown_type](#))(void)
- typedef void * [input_plugin_handle_type](#)
- typedef float(* [input_can_handle_type](#))(const char *path)
- typedef int(* [input_open_type](#))(input_object *obj, const char *path)
- typedef void(* [input_close_type](#))(input_object *obj)
- typedef int(* [input_play_frame_type](#))(input_object *obj, char *buffer)
- typedef int(* [input_frame_seek_type](#))(input_object *obj, int frame)
- typedef int(* [input_frame_size_type](#))(input_object *obj)
- typedef int(* [input_nr_frames_type](#))(input_object *obj)
- typedef long(* [input_frame_to_sec_type](#))(input_object *obj, int frame)
- typedef int(* [input_sample_rate_type](#))(input_object *obj)
- typedef int(* [input_channels_type](#))(input_object *obj)
- typedef int(* [input_stream_info_type](#))(input_object *obj, stream_info *info)
- typedef int(* [input_nr_tracks_type](#))(input_object *obj)
- typedef int(* [input_track_seek_type](#))(input_object *obj, int track)
- typedef struct [_input_plugin](#) input_plugin
- typedef [input_plugin](#) *(* [input_plugin_info_type](#))(void)

4.1.1 Define Documentation

4.1.1.1 #define INPUT_PLUGIN_BASE_VERSION 0x1000

The base version number of the scope plugin. Set at 0x1000.

4.1.1.2 #define INPUT_PLUGIN_VERSION (INPUT_PLUGIN_BASE_VERSION + 16)

The version of the input plugin API. This should be incremented whenever structural changes are made to the API. This value should only be changed by the maintainers.

4.1.1.3 #define P_BUFFERING 32

Set minimal buffer

4.1.1.4 #define P_FILEBASED 8

Set this flag if the stream is file based (local disk file)

4.1.1.5 `#define P_PERFECTSEEK 2`

Set this flag if your plugin is able to do sample accurate seeking in the stream. This is required for reverse speed playback.

4.1.1.6 `#define P_REENTRANT 4`

Set this flag if your plugin is reentrant.

4.1.1.7 `#define P_SEEK 1`

Set this flag if your plugin is able to seek in the stream

4.1.1.8 `#define P_STREAMBASED 16`

Set this if the stream is a real stream e.g. HTTP or UDP based

4.1.2 Typedef Documentation

4.1.2.1 `typedef float(* input_can_handle_type)(const char *path)`

Parameters:

path Path to stream

Returns a rating between 0.0 and 1.0 for how well this plugin can handle the given path
1.0 = Excellent 0.0 = Huh?

4.1.2.2 `typedef int(* input_channels_type)(input_object *obj)`

Parameters:

obj input object

Returns number of channels in the stream

4.1.2.3 `typedef void(* input_close_type)(input_object *obj)`

Parameters:

obj input object

Close stream

4.1.2.4 `typedef int input_flags_type`

Capability flags for this plugin

4.1.2.5 `typedef int(* input_frame_seek_type)(input_object *obj, int frame)`

Parameters:

obj input object

frame Seek to a specific frame number

4.1.2.6 `typedef int(* input_frame_size_type)(input_object *obj)`

Parameters:

obj input object

Returns the frame size in bytes

4.1.2.7 `typedef long(* input_frame_to_sec_type)(input_object *obj, int frame)`

Parameters:

obj input object

frame frame number

Returns the offset from the start time in centiseconds (100th of a second) for the frame given.

4.1.2.8 `typedef int(* input_init_type)(void)`

Init plugin

4.1.2.9 `typedef int(* input_nr_frames_type)(input_object *obj)`

Parameters:

obj input object

Returns the total number of frames in the stream

4.1.2.10 typedef int(* input_nr_tracks_type)(input_object *obj)**Parameters:**

obj input object

Return number of tracks. Optional

4.1.2.11 typedef struct _input_object input_object

This is a structure that keeps frequently used parameters of an input instance. It also contains a pointer to any local_data that might be allocated by the plugin itself.

4.1.2.12 typedef int(* input_open_type)(input_object *obj, const char *path)**Parameters:**

obj input object

path path of stream to open

Open stream

4.1.2.13 typedef int(* input_play_frame_type)(input_object *obj, char *buffer)**Parameters:**

obj input object

buffer buffer where we should write the frame to

Play/decode a single frame. This function should write exactly one frame to the buffer. If there is not enough PCM data to fill the frame it should be padded with zeros (silence).

4.1.2.14 typedef struct _input_plugin input_plugin**4.1.2.15 typedef void* input_plugin_handle_type**

Handle for plugin. Filled in by the host

4.1.2.16 typedef input_plugin*(* input_plugin_info_type)(void)

Every input plugin should have an input_plugin_info() function that returns a pointer to an input_plugin structure that is set up with pointers to your implementations. If

your plugin is compiled using C++ make sure you 'extern "C"' the `input_plugin_info()` function or else the HOST will not be able to load the plugin.

4.1.2.17 `typedef int(* input_sample_rate_type)(input_object *obj)`

Parameters:

obj input object

Returns the sample rate of the stream

4.1.2.18 `typedef void(* input_shutdown_type)(void)`

Prepare the plugin for removal

4.1.2.19 `typedef int(* input_stream_info_type)(input_object *obj, stream_info *info)`

Parameters:

obj input object

info pointer to stream_info structure

Return stream info of the current stream. You should not allocate space for the stream_info structure. The HOST will take care of that.

4.1.2.20 `typedef int(* input_track_seek_type)(input_object *obj, int track)`

4.1.2.21 `typedef int input_version_type`

input plugin binary version. Must be set to `INPUT_PLUGIN_VERSION`

4.2 interface_plugin.h File Reference

```
#include "CorePlayer.h"
#include "Playlist.h"
```

Data Structures

- struct [_interface_plugin](#)

Defines

- #define [INTERFACE_PLUGIN_BASE_VERSION](#) 0x1000
- #define [INTERFACE_PLUGIN_VERSION](#) (INTERFACE_PLUGIN_BASE_VERSION + 4)

Typedefs

- typedef int [interface_version_type](#)
- typedef int(* [interface_init_type](#))()
- typedef int(* [interface_start_type](#))(Playlist *, int, char **)
- typedef int(* [interface_running_type](#))()
- typedef int(* [interface_stop_type](#))()
- typedef void(* [interface_close_type](#))()
- typedef struct [_interface_plugin](#) [interface_plugin](#)
- typedef [interface_plugin](#) *(* [interface_plugin_info_type](#))()

4.2.1 Define Documentation

4.2.1.1 `#define INTERFACE_PLUGIN_BASE_VERSION 0x1000`

4.2.1.2 `#define INTERFACE_PLUGIN_VERSION (INTERFACE_PLUGIN_BASE_VERSION + 4)`

4.2.2 Typedef Documentation

4.2.2.1 `typedef void(* interface_close_type)()`

4.2.2.2 `typedef int(* interface_init_type)()`

4.2.2.3 `typedef struct _interface_plugin interface_plugin`

4.2.2.4 `typedef interface_plugin(* interface_plugin_info_type)()`

4.2.2.5 `typedef int(* interface_running_type)()`

4.2.2.6 `typedef int(* interface_start_type)(Playlist *, int, char **)`

4.2.2.7 `typedef int(* interface_stop_type)()`

4.2.2.8 `typedef int interface_version_type`

4.3 output_plugin.h File Reference

Data Structures

- struct [_output_plugin](#)

Defines

- #define [OUTPUT_PLUGIN_BASE_VERSION](#) 0x1000
- #define [OUTPUT_PLUGIN_VERSION](#) (OUTPUT_PLUGIN_BASE_VERSION + 6)

Typedefs

- typedef int [output_version_type](#)
- typedef int(* [output_init_type](#))(void)
- typedef int(* [output_open_type](#))(const char *path)
- typedef void(* [output_close_type](#))(void)
- typedef int(* [output_write_type](#))(void *data, int byte_count)
- typedef int(* [output_start_callbacks_type](#))(void *data)
- typedef int(* [output_set_buffer_type](#))(int *frag_size, int *frag_count, int *channels)
- typedef unsigned int(* [output_set_sample_rate_type](#))(unsigned int rate)
- typedef int(* [output_get_queue_count_type](#))(void)
- typedef int(* [output_get_latency_type](#))(void)
- typedef struct [_output_plugin](#) output_plugin
- typedef [output_plugin](#) *(* [output_plugin_info_type](#))(void)

4.3.1 Define Documentation

4.3.1.1 `#define OUTPUT_PLUGIN_BASE_VERSION 0x1000`

4.3.1.2 `#define OUTPUT_PLUGIN_VERSION (OUTPUT_PLUGIN_BASE_VERSION + 6)`

4.3.2 Typedef Documentation

4.3.2.1 `typedef void(* output_close_type)(void)`

4.3.2.2 `typedef int(* output_get_latency_type)(void)`

4.3.2.3 `typedef int(* output_get_queue_count_type)(void)`

4.3.2.4 `typedef int(* output_init_type)(void)`

4.3.2.5 `typedef int(* output_open_type)(const char *path)`

4.3.2.6 `typedef struct _output_plugin output_plugin`

4.3.2.7 `typedef output_plugin(* output_plugin_info_type)(void)`

4.3.2.8 `typedef int(* output_set_buffer_type)(int *frag_size, int *frag_count, int *channels)`

4.3.2.9 `typedef unsigned int(* output_set_sample_rate_type)(unsigned int rate)`

4.3.2.10 `typedef int(* output_start_callbacks_type)(void *data)`

4.3.2.11 `typedef int output_version_type`

4.3.2.12 `typedef int(* output_write_type)(void *data, int byte_count)`

4.4 scope_plugin.h File Reference

Data Structures

- struct [_scope_plugin](#)

Defines

- #define [SCOPE_PLUGIN_BASE_VERSION](#) 0x1000
- #define [SCOPE_PLUGIN_VERSION](#) (SCOPE_PLUGIN_BASE_VERSION + 7)
- #define [SCOPE_NICE](#) 10
- #define [SCOPE_SLEEP](#) 20000
- #define [SCOPE_BG_RED](#) 0
- #define [SCOPE_BG_GREEN](#) 0
- #define [SCOPE_BG_BLUE](#) 0

Typedefs

- typedef int [scope_version_type](#)
- typedef int(* [scope_init_type](#))(void *arg)
- typedef void(* [scope_start_type](#))(void)
- typedef int(* [scope_running_type](#))(void)
- typedef void(* [scope_stop_type](#))(void)
- typedef void(* [scope_shutdown_type](#))(void)
- typedef void(* [scope_set_data_type](#))(void *buffer, int count)
- typedef void(* [scope_set_fft_type](#))(void *buffer, int samples, int channels)
- typedef struct [_scope_plugin](#) [scope_plugin](#)
- typedef [scope_plugin](#) *(* [scope_plugin_info_type](#))(void)

4.4.1 Define Documentation

4.4.1.1 #define SCOPE_BG_BLUE 0

The value of the BLUE component of the default background color for scope windows. Value should be from 0-255

4.4.1.2 #define SCOPE_BG_GREEN 0

The value of the GREEN component of the default background color for scope windows. Value should be from 0-255

4.4.1.3 `#define SCOPE_BG_RED 0`

The value of the RED component of the default background color for scope windows. Value should be from 0-255

4.4.1.4 `#define SCOPE_NICE 10`

The default nice level scope plugins should be set at. Most scope plugins are just eye candy and as such should not interfere with other processes on your system. They should only use CPU cycles that would otherwise be wasted. Setting the scopes to a nice level of 10 or higher pretty much insures this. If you don't like this policy you can lower the value. Keep in mind that negative values will only work if you run the HOST as root

4.4.1.5 `#define SCOPE_PLUGIN_BASE_VERSION 0x1000`

The base version number of the scope plugin. Set at 0x1000

4.4.1.6 `#define SCOPE_PLUGIN_VERSION (SCOPE_PLUGIN_BASE_VERSION + 7)`

The version of the scope plugin API. This should be increased whenever structural changes are made to the API. This value should only be changed by the maintainers.

4.4.1.7 `#define SCOPE_SLEEP 20000`

The default sleep time in microseconds for scopes. After every render iteration a scope should sleep for this amount of time. You should use the `dosleep()` call i.e. `dosleep(SCOPE_SLEEP)`. A value of 20000 will let scopes run at $100000/20000 = 50$ frames per second. If the scopes are consuming too much CPU consider raising this value.

4.4.2 Typedef Documentation

4.4.2.1 `typedef int(* scope_init_type)(void *arg)`

The init function of a scope plugin. This function should initialize all data structures needed for the scope plugin. Return value should be 1 on success, 0 if initialization fails.

Parameters:

Set to NULL. This currently used for internal plugins only

4.4.2.2 typedef struct _scope_plugin scope_plugin

You should declare a scope_plugin variable and populate it with pointers of the specific functions implemented by your scope

4.4.2.3 typedef scope_plugin*(* scope_plugin_info_type)(void)

Every scope plugin should have a scope_plugin_info() function that returns a pointer to a scope_plugin structure that is filled with pointers to your function implementations.

4.4.2.4 typedef int(* scope_running_type)(void)

This function should tell the HOST if the scope is running i.e. on-screen and rendering. A value of 1 should be returned if this is the case, 0 if the scope is not active.

4.4.2.5 typedef void(* scope_set_data_type)(void *buffer, int count)

Parameters:

buffer pointer to buffer data

count number of short (int16) samples in buffer

The set_data function should be defined if your scope wants to get it hands on PCM data. The format of the buffer is short (int16) interleaved stereo data. A count value of 1024 means there are 2048 short samples in the buffer. These samples are interleaved, so even sample positions are from the left channel, uneven sample positions from the right channel. The API will be changed to accommodate variable channels in the not too distant future.

4.4.2.6 typedef void(* scope_set_fft_type)(void *buffer, int samples, int channels)

Parameters:

buffer buffer with FFT values

samples number of FFT values per channel

channels number of channels

This function should be defined if your scope wants to get FFT data. The HOST typically calculates 256 FFT values per channel (going from low frequency range to high). The value is between 0-256. The buffer format is NON-interleaved int (int32). So if samples = 256 and channels = 2 then there are 2 * 256 number of samples in the buffer. The first 256 are for channel 1, the other 256 for channel 2.

4.4.2.7 typedef void(* scope_shutdown_type)(void)

The shutdown function is called just before the plugin is unloaded or just before the HOST decides to exit. All data structures allocated in the init routine should be freed here.

4.4.2.8 typedef void(* scope_start_type)(void)

This function will be called when the HOST wants to activate the scope. It should pop up the scope window and start rendering the PCM or FFT data

4.4.2.9 typedef void(* scope_stop_type)(void)

This function should stop and close the scope window if it was running. It should just return if the scope is not running.

4.4.2.10 typedef int scope_version_type

The API this scope was compiled against. It should always be set to SCOPE_PLUGIN_VERSION. Failing to set this will most likely result in a scope plugin that won't load.

Index

- [_input_object, 5](#)
 - [flags, 6](#)
 - [frame_size, 6](#)
 - [local_data, 6](#)
 - [nr_channels, 6](#)
 - [nr_frames, 6](#)
 - [nr_tracks, 6](#)
 - [object_mutex, 6](#)
 - [path, 6](#)
 - [ready, 6](#)
 - [_input_plugin, 8](#)
 - [author, 8](#)
 - [can_handle, 8](#)
 - [channels, 8](#)
 - [close, 8](#)
 - [flags, 8](#)
 - [frame_seek, 8](#)
 - [frame_size, 9](#)
 - [frame_to_sec, 9](#)
 - [handle, 9](#)
 - [init, 9](#)
 - [name, 9](#)
 - [nr_frames, 9](#)
 - [nr_tracks, 9](#)
 - [open, 9](#)
 - [play_frame, 9](#)
 - [plugin_handle, 9](#)
 - [sample_rate, 9](#)
 - [shutdown, 9](#)
 - [stream_info, 9](#)
 - [track_seek, 9](#)
 - [version, 9](#)
 - [_interface_plugin, 10](#)
 - [author, 10](#)
 - [close, 10](#)
 - [handle, 10](#)
 - [init, 10](#)
 - [name, 10](#)
 - [running, 10](#)
 - [start, 10](#)
 - [stop, 10](#)
 - [version, 10](#)
 - [_output_plugin, 11](#)
 - [author, 11](#)
 - [close, 11](#)
 - [get_latency, 11](#)
 - [get_queue_count, 11](#)
 - [init, 11](#)
 - [name, 11](#)
 - [open, 12](#)
 - [set_buffer, 12](#)
 - [set_sample_rate, 12](#)
 - [start_callbacks, 12](#)
 - [version, 12](#)
 - [write, 12](#)
 - [_scope_plugin, 14](#)
 - [author, 14](#)
 - [handle, 14](#)
 - [init, 14](#)
 - [name, 14](#)
 - [running, 14](#)
 - [set_data, 15](#)
 - [set_fft, 15](#)
 - [shutdown, 15](#)
 - [start, 15](#)
 - [stop, 15](#)
 - [version, 15](#)
- [author](#)
 - [_input_plugin, 8](#)
 - [_interface_plugin, 10](#)
 - [_output_plugin, 11](#)
 - [_scope_plugin, 14](#)

- can_handle
 - _input_plugin, 8
- channels
 - _input_plugin, 8
- close
 - _input_plugin, 8
 - _interface_plugin, 10
 - _output_plugin, 11
- flags
 - _input_object, 6
 - _input_plugin, 8
- frame_seek
 - _input_plugin, 8
- frame_size
 - _input_object, 6
 - _input_plugin, 9
- frame_to_sec
 - _input_plugin, 9
- get_latency
 - _output_plugin, 11
- get_queue_count
 - _output_plugin, 11
- handle
 - _input_plugin, 9
 - _interface_plugin, 10
 - _scope_plugin, 14
- init
 - _input_plugin, 9
 - _interface_plugin, 10
 - _output_plugin, 11
 - _scope_plugin, 14
- input_can_handle_type
 - input_plugin.h, 19
- input_channels_type
 - input_plugin.h, 19
- input_close_type
 - input_plugin.h, 19
- input_flags_type
 - input_plugin.h, 19
- input_frame_seek_type
 - input_plugin.h, 20
- input_frame_size_type
 - input_plugin.h, 20
- input_frame_to_sec_type
 - input_plugin.h, 20
- input_init_type
 - input_plugin.h, 20
- input_nr_frames_type
 - input_plugin.h, 20
- input_nr_tracks_type
 - input_plugin.h, 20
- input_object
 - input_plugin.h, 21
- input_open_type
 - input_plugin.h, 21
- input_play_frame_type
 - input_plugin.h, 21
- input_plugin
 - input_plugin.h, 21
- input_plugin.h, 17
 - input_can_handle_type, 19
 - input_channels_type, 19
 - input_close_type, 19
 - input_flags_type, 19
 - input_frame_seek_type, 20
 - input_frame_size_type, 20
 - input_frame_to_sec_type, 20
 - input_init_type, 20
 - input_nr_frames_type, 20
 - input_nr_tracks_type, 20
 - input_object, 21
 - input_open_type, 21
 - input_play_frame_type, 21
 - input_plugin, 21
 - INPUT_PLUGIN_BASE_VERSION, 18
 - input_plugin_handle_type, 21
 - input_plugin_info_type, 21
 - INPUT_PLUGIN_VERSION, 18
 - input_sample_rate_type, 22
 - input_shutdown_type, 22
 - input_stream_info_type, 22
 - input_track_seek_type, 22
 - input_version_type, 22
 - P_BUFFERING, 18
 - P_FILEBASED, 18
 - P_PERFECTSEEK, 18
 - P_REENTRANT, 19

- P_SEEK, 19
- P_STREAMBASED, 19
- INPUT_PLUGIN_BASE_VERSION
 - input_plugin.h, 18
- input_plugin_handle_type
 - input_plugin.h, 21
- input_plugin_info_type
 - input_plugin.h, 21
- INPUT_PLUGIN_VERSION
 - input_plugin.h, 18
- input_sample_rate_type
 - input_plugin.h, 22
- input_shutdown_type
 - input_plugin.h, 22
- input_stream_info_type
 - input_plugin.h, 22
- input_track_seek_type
 - input_plugin.h, 22
- input_version_type
 - input_plugin.h, 22
- interface_close_type
 - interface_plugin.h, 24
- interface_init_type
 - interface_plugin.h, 24
- interface_plugin
 - interface_plugin.h, 24
- interface_plugin.h, 23
 - interface_close_type, 24
 - interface_init_type, 24
 - interface_plugin, 24
- INTERFACE_PLUGIN_BASE_VERSION, 24
 - interface_plugin_info_type, 24
- INTERFACE_PLUGIN_VERSION, 24
 - interface_running_type, 24
 - interface_start_type, 24
 - interface_stop_type, 24
 - interface_version_type, 24
- INTERFACE_PLUGIN_BASE_VERSION
 - interface_plugin.h, 24
- interface_plugin_info_type
 - interface_plugin.h, 24
- INTERFACE_PLUGIN_VERSION
 - interface_plugin.h, 24
- interface_running_type
 - interface_plugin.h, 24
- interface_start_type
 - interface_plugin.h, 24
- interface_stop_type
 - interface_plugin.h, 24
- interface_version_type
 - interface_plugin.h, 24
- local_data
 - _input_object, 6
- name
 - _input_plugin, 9
 - _interface_plugin, 10
 - _output_plugin, 11
 - _scope_plugin, 14
- nr_channels
 - _input_object, 6
- nr_frames
 - _input_object, 6
 - _input_plugin, 9
- nr_tracks
 - _input_object, 6
 - _input_plugin, 9
- object_mutex
 - _input_object, 6
- open
 - _input_plugin, 9
 - _output_plugin, 12
- output_close_type
 - output_plugin.h, 26
- output_get_latency_type
 - output_plugin.h, 26
- output_get_queue_count_type
 - output_plugin.h, 26
- output_init_type
 - output_plugin.h, 26
- output_open_type
 - output_plugin.h, 26
- output_plugin
 - output_plugin.h, 26
- output_plugin.h, 25
 - output_close_type, 26
 - output_get_latency_type, 26

- output_get_queue_count_type, 26
- output_init_type, 26
- output_open_type, 26
- output_plugin, 26
- OUTPUT_PLUGIN_BASE_VERSION, 26
- output_plugin_info_type, 26
- OUTPUT_PLUGIN_VERSION, 26
- output_set_buffer_type, 26
- output_set_sample_rate_type, 26
- output_start_callbacks_type, 26
- output_version_type, 26
- output_write_type, 26
- OUTPUT_PLUGIN_BASE_VERSION
 - output_plugin.h, 26
- output_plugin_info_type
 - output_plugin.h, 26
- OUTPUT_PLUGIN_VERSION
 - output_plugin.h, 26
- output_set_buffer_type
 - output_plugin.h, 26
- output_set_sample_rate_type
 - output_plugin.h, 26
- output_start_callbacks_type
 - output_plugin.h, 26
- output_version_type
 - output_plugin.h, 26
- output_write_type
 - output_plugin.h, 26
- P_BUFFERING
 - input_plugin.h, 18
- P_FILEBASED
 - input_plugin.h, 18
- P_PERFECTSEEK
 - input_plugin.h, 18
- P_REENTRANT
 - input_plugin.h, 19
- P_SEEK
 - input_plugin.h, 19
- P_STREAMBASED
 - input_plugin.h, 19
- path
 - _input_object, 6
- play_frame
 - _input_plugin, 9
- plugin_handle
 - _input_plugin, 9
- ready
 - _input_object, 6
- running
 - _interface_plugin, 10
 - _scope_plugin, 14
- sample_rate
 - _input_plugin, 9
- SCOPE_BG_BLUE
 - scope_plugin.h, 27
- SCOPE_BG_GREEN
 - scope_plugin.h, 27
- SCOPE_BG_RED
 - scope_plugin.h, 27
- scope_init_type
 - scope_plugin.h, 28
- SCOPE_NICE
 - scope_plugin.h, 28
- scope_plugin
 - scope_plugin.h, 29
- scope_plugin.h, 27
 - SCOPE_BG_BLUE, 27
 - SCOPE_BG_GREEN, 27
 - SCOPE_BG_RED, 27
 - scope_init_type, 28
 - SCOPE_NICE, 28
 - scope_plugin, 29
 - SCOPE_PLUGIN_BASE_VERSION, 28
 - scope_plugin_info_type, 29
 - SCOPE_PLUGIN_VERSION, 28
 - scope_running_type, 29
 - scope_set_data_type, 29
 - scope_set_fft_type, 29
 - scope_shutdown_type, 29
 - SCOPE_SLEEP, 28
 - scope_start_type, 30
 - scope_stop_type, 30
 - scope_version_type, 30

SCOPE_PLUGIN_BASE_VERSION
 scope_plugin.h, [28](#)
scope_plugin_info_type
 scope_plugin.h, [29](#)
SCOPE_PLUGIN_VERSION
 scope_plugin.h, [28](#)
scope_running_type
 scope_plugin.h, [29](#)
scope_set_data_type
 scope_plugin.h, [29](#)
scope_set_fft_type
 scope_plugin.h, [29](#)
scope_shutdown_type
 scope_plugin.h, [29](#)
SCOPE_SLEEP
 scope_plugin.h, [28](#)
scope_start_type
 scope_plugin.h, [30](#)
scope_stop_type
 scope_plugin.h, [30](#)
scope_version_type
 scope_plugin.h, [30](#)
set_buffer
 _output_plugin, [12](#)
set_data
 _scope_plugin, [15](#)
set_fft
 _scope_plugin, [15](#)
set_sample_rate
 _output_plugin, [12](#)
shutdown
 _input_plugin, [9](#)
 _scope_plugin, [15](#)
start
 _interface_plugin, [10](#)
 _scope_plugin, [15](#)
start_callbacks
 _output_plugin, [12](#)
stop
 _interface_plugin, [10](#)
 _scope_plugin, [15](#)
stream_info
 _input_plugin, [9](#)

track_seek
 _input_plugin, [9](#)

version
 _input_plugin, [9](#)
 _interface_plugin, [10](#)
 _output_plugin, [12](#)
 _scope_plugin, [15](#)

write
 _output_plugin, [12](#)